

Introduction

Thank you for choosing Siglos Karaoke Professional.

Siglos Karaoke Professional is a karaoke show manager that allows you to keep song database, and helps to run karaoke shows by the means managing singers, songs, and rotation.

Siglos Karaoke Professional is also an advanced karaoke player that can play karaoke songs in various formats (including CD+G and MIDI Karaoke) and record your voice while you sing along.

The program has two modes of operation -- professional and basic. Professional mode should be used when running a show, while basic mode is for everyday use. To switch the mode go to **Settings** dialog box, select **KJ** section, and change **Use professional KJ mode** option.

- [Main window controls](#)
- [Getting karaoke songs](#)
- [Keyboard shortcuts](#)
- [Supported file types](#)
- [Troubleshooting](#)
- [Unlocking and evaluation](#)


Main window controls



Getting karaoke songs

Internet is full of MIDI karaoke files and Siglos Karaoke Player provides a simple tool to help you find them.

To start MIDI karaoke web search select **Search for karaoke on the Internet** command from **Tools** menu.



To start the search you need to provide artist name and the title of the song. Note that the song title does not have to be complete -- you may enter just first couple of words.

Search engine combo allows you to change the place that you will use to search for files. You may try changing search engine if you are not getting the results you need.

Clicking on **OK** button will open the search in your web browser. Once you find the file save it to your hard disc and open it later using **Load file** button.

Disclaimer: Doblon does not provide MIDI karaoke files. They are provided by various websites that are not affiliated with us.

Keyboard shortcuts

The easiest way to control the playback is to use **multimedia buttons** on your keyboard. In addition to basic functions extra functionality is provided with CTRL and SHIFT keys:

Volume Up + CTRL	Key Up
Volume Down + CTRL	Key Down
Volume Up + SHIFT	Tempo Up
Volume Down + SHIFT	Tempo Down
Next Track + CTRL	Fast Forward
Prev Track + CTRL	Rewind

Professional mode:

Next Track or F5	Start song / Go to next song
Prev Track of Ctrl+F5	Restart playing song
F6	Add Singer
F7	Song Database
F8	Import Songs
Volume Up + SHIFT or {	Tempo down
Volume Dn + SHIFT or }	Tempo up

<i>In song list</i>	
DEL	Remove song
Enter	Move song to next

<i>In singer list</i>	
DEL	Remove singer
Enter	Move singer to next
Space	Add songs to singer
Ctrl+D	Disable singer

Supported file types

Siglos Karaoke Professional currently supports following types of files:

File extension	Description
.cdg	Also known as MP3+G. CDG files are usually paired with MP3 file CDG file contains lyrics, while MP3 file contains audio of the song open a pair of MP3/CDG files you need to open CDG file only
.bin	BIN files contain both lyrics and audio of CD+G song
.zip	Karaoke ZIP files contain pairs of CDG/MP3 files
.cda	CD+G disc tracks
.kar, .mid	MIDI Karaoke
.avi	AVI video files
.mpg	MPG video files
.kma	MTU's Hoster files
.wmv	Windows Media Video files
.mp4, .mpeg, .mov, .webm, .mkv	Video tracks

Troubleshooting

[I play CD+Gs and see no lyrics](#)

[I play CD+G discs and graphics are damaged](#)

[I cannot record my voice](#)

[My second monitor does not work with Siglos Karaoke Professional](#)

[Siglos icons are too small/too large](#)

[YouTube playback does not work](#)

If there are some other problems please contact technical support at support@powerkaraoke.com.

I play CD+Gs and see no lyrics

- Your CD-ROM may not be able to read CD+G data. If you have more than one CD-ROMs in your computer, please try the other device.

I play CD+G discs and graphics are damaged

- Your CD+G disc may be scratched -- it downgrades the video quality. Some CD-ROM drives are better at reading damaged discs, so if you have more than one installed in your computer, please try the other one.

I cannot record my voice

- Check if your microphone is connected properly. Use [Recording settings](#) to set up recording levels.


My second monitor does not work with Siglos Karaoke Professional

- Always plug your TV monitor in and turn it on before turning your computer on. If not, your dual display card will come up in single-display mode.
- With multiple monitors, one will be your Primary display (for you to operate by) and the other your Secondary display (for singers).


Siglos icons are too small/too large

Try changing DPI compatibility settings. To do this:


1. Right click **Siglos** icon and choose **Properties**



2. Choose **Compatibility** tab and click **Change high DPI settings**



3. Try setting to this options. If it does not work, change **High DPI scaling override** to **Application**



YouTube playback does not work

As Siglos is not an official YouTube player and uses yt-dlp software for this feature, it may happen that YouTube servers block access. This can occur if you download too many files or use YouTube playback too much. As a solution, you may connect your YouTube account to Siglos. To do this, open **Settings** in the **Play From YouTube** window and choose the browser you are using in the **Use cookies from browser** field. Unfortunately, Chrome does not fully support this, so if you still encounter errors after selecting Chrome, try installing **Firefox** and logging in to YouTube with it. You do not need to make it your default browser. Then choose **Firefox** in the **Use cookies from browser** field.

If this still does not help, it means your IP was banned from automatic access to YouTube. You may try changing your IP if possible (sometimes disconnecting your router/modem does that) or connecting via VPN. Usually, the ban is removed after a few days.

Unlocking and evaluation

How do I unlock Siglos Karaoke Player

To unlock Siglos Karaoke Player you need to purchase the unlock code from [Power Karaoke website](#). The unlock code will be delivered via email. Once you have it select **Unlock** from **Help** menu.

You will have to provide your name, email address used to purchase the unlock code, and the unlock code itself. If the unlock code is accepted all limitations will be removed and you will see your name in the About dialog box.

What are the limitation of the trial version

Trial version of Siglos Karaoke Player has the following limitations:

- Only two minutes of the song will be played
- Banner will be displayed over the lyrics
- Only one minute of your singing will be recorded
- You will see the purchase prompt from time to time